

8) E-mail server configuration for work with Ozols TMS


1. [Gmail settings](#)
2. [Microsoft Settings](#)

1. To send Gmail emails from within OZOLS TMS, follow these steps:

1) Open a Google account and authorize:


<https://myaccount.google.com/>

2) Opens the **Security section**



3) Activate **two-step** authentication (a confirmation code will be sent to the phone)

Signing in to Google




Password Last changed Jul 21, 2009 >

Use your phone to sign in ☐ Off >

2-Step Verification ☐ Off **2** >

4) Select App passwords

Signing in to Google



Password Last changed Jul 21, 2009 >

2-Step Verification ☒ On >

App passwords None >

4) Choose Other (Custom name)

← App passwords

App passwords let you sign in to your Google Account from apps on devices that don't support 2-Step Verification. You'll only need to enter it once so you don't need to remember it. [Learn more](#)

You don't have any app passwords.

Select the app and device you want to generate the app password for.

Select app Select device

Mail

Calendar

Contacts

YouTube

Other (Custom name)

GENERATE

5) Type "Ozols" in the window and press **GENERATE**

← App passwords

App passwords let you sign in to your Google Account from apps on devices that don't support 2-Step Verification. You'll only need to enter it once so you don't need to remember it. [Learn more](#)

You don't have any app passwords.

Select the app and device you want to generate the app password for.

X

GENERATE

5) A gmail password for the OZOLS TMS system is created

Generated app password

Your app password for your device

avvv evom dzto tkdd

How to use it

Go to the settings for your Google Account in the application or device you are trying to set up. Replace your password with the 16-character password shown above. Just like your normal password, this app password grants complete access to your Google Account. You won't need to remember it, so don't write it down or share it with anyone.

DONE

Email

Password

5) This password must be entered in the user's email settings in OZOLS TMS by following the [instructions here](#).

2. To send Microsoft e-mails from OZOLS TMS, you must perform the following steps:

1. Open the following link and sign in to your Microsoft account:



Sign in

Email or phone

[Can't access your account?](#)

Next

2.

My Sign-Ins

Overview

Security info

Devices

Password

Organisations

Settings & Privacy

Recent activity

Security info

These are the methods you use to sign into your account or reset your password.

You're using the most advisable sign-in method where it applies.
Sign-in method when most advisable is unavailable: Microsoft Authenticator - notification [Change](#)

+ Add sign-in method

Phone	+45 60555810
Password	Last updated: 3 years ago
App password	OZOLS TMS
Microsoft Authenticator Push multi-factor authentication (MFA)	iPhone 16 Pro

Lost device? [Sign out everywhere](#)

App password

App password was successfully created. Copy the password to clipboard and paste into your app. Then return here and choose 'Done'

Name: OZOLS TMS

Password: scv1#h1xqgqhmfn

Note: Keep this password in a safe place. It will not be shown again.

Back Done

3. Select > Add method > App password

Add a method

Which method would you like to add?

App password

Cancel Add

4. Copy the password created by Microsoft

App password



App password was successfully created. Copy the password to clipboard and paste into your app. Then return here and choose 'Done'

Name:

SMTP connection

Password:

czkbvdcyvtlckzkm



Note: Keep this password in a safe place. It will not be shown again.

Back

Done

5. This password must be entered in the user's email settings in OZOLS TMS by following the [instructions here](#).

Revision #3

Created Wed, Aug 31, 2022 9:27 AM by [Janis Veldre](#)

Updated Mon, May 12, 2025 12:17 PM by [Janis Veldre](#)